



DxO Optics Pro v6.1.1 – Release Notes

Windows (build 7525)

Supported Systems

- Windows XP (32-bit and 64-bit)
- Windows Vista (32-bit and 64-bit)
- Windows 7 (32-bit and 64-bit)

Installation

- The .NET 3.5 SP1 Framework will be installed if not already present on the machine (it may take several minutes; a reboot is required).
- Installing the latest updates of Windows is recommended before installing the application.

New features

- New supported camera body: Canon S90

Third party software compatibility

- Lightroom: support for both Lightroom 1.4 and 2.x

Improvements since version 6.1.0

- Optical corrections are now available again when using DxO Optics Pro as a Lightroom 2.x external editor.

Known limitations

- Some Canon bodies perform vignetting correction for JPEG images. DxO Optics Pro does not take into account the correction performed by the camera body. DxO Optics Correction Modules have been created using shots with vignetting body correction disabled. For optimal correction of vignetting by DxO Optics Pro, we recommend disabling the in-camera body vignetting correction while shooting.
- Lightroom 2.0 smart collections are not accessible from DxO Optics Pro.
- Stability issues in some rare cases or configurations.
- With Vista, ICC profiles v4 with gamma table are not correctly supported